CSD Release and Installation Notes

2020.1 CSD Release

Copyright © 2020 Cambridge Crystallographic Data Centre Registered Charity No 800579

Conditions of Use

The Cambridge Structural Database System (CSD System) comprising all or some of the following: ConQuest, CSD-Editor, Decifer, Mercury, Mercury CSD, CSD-Materials (formerly known as the Solid Form or Materials module of Mercury), Mogul, IsoStar, DASH, SuperStar, web accessible CSD tools and services, WebCSD, CSD sketchers, CSD data files, CSD data updates, the CSD database, sub-files derived from the foregoing data files, documentation and command procedures, test versions of any existing or new program, code, tool, data files, sub-files, documentation or command procedures which may be available from time to time (each individually a Component) is a database and copyright work belonging to the Cambridge Crystallographic Data Centre (CCDC) and its licensors and all rights are protected.

Use of the CSD System is permitted solely in accordance with a valid Licence of Access Agreement or Products Licence and Support Agreement and all Components included are proprietary. When a Component is supplied independently of the CSD System its use is subject to the conditions of the separate licence. All persons accessing the CSD System or its Components should make themselves aware of the conditions contained in the Licence of Access Agreement or Products Licence and Support Agreement or the relevant licence.

In particular:

- The CSD System and its Components are licensed subject to a time limit for use by a specified organisation at a specified location.
- The CSD System and its Components are to be treated as confidential and may NOT be disclosed or re-distributed in any form, in whole or in part, to any third party.
- Software or data derived from or developed using the CSD System may not be distributed without prior written approval of the CCDC. Such prior approval is also needed for joint projects between academic and for-profit organisations involving use of the CSD System.
- The CSD System and its Components may be used for scientific research, including the design of novel compounds. Results may be published in the scientific literature, but each such publication must include an appropriate citation as indicated in the Schedule to the Licence of Access Agreement or Products Licence and Support Agreement and on the CCDC website.
- No representations, warranties, or liabilities are expressed or implied in the supply of the CSD System or its Components by CCDC, its servants or agents, except where such exclusion or limitation is prohibited, void or unenforceable under governing law.

Licences may be obtained from:

Cambridge Crystallographic Data Centre 12 Union Road Cambridge CB2 1EZ, United Kingdom

Web:http://www.ccdc.cam.ac.ukTelephone:+44-1223-336408Email:admin@ccdc.cam.ac.uk

Contents

1	CSD Re	CSD Release Package1		
2	Database Content and Information2			
3	What's	What's New		
4	Known Problems			4
5	Installation Overview			5
	5.2	5.2 System Requirements		5
		5.2.1	Supported Platforms	5
		5.2.2	Changes to Supported Platforms and Products	5
		5.2.3	Graphics System Requirements	6
		5.2.4	Access of CSD software by X-forwarding	6
		5.2.5	Stereoscopic Viewing Graphical System Requirements	6
		5.2.6	Disk Space Requirements	6
6	Windo	ws Install	ation	7
	6.1	General	Installation Options	7
	6.2	Installat	ion Procedure	7
	6.3	Uninsta	lling CSD System Software and Database files	7
7	Linux I	nstallatio	n	8
	7.1	Package	e Requirements	8
	7.2	Installat	ion Procedure	8
	7.3	IsoStar S	Server Installation	8
8	macOS	5 Installati	ion	9
	8.1	General	Installation Process	9
	8.2	Installat	ion Procedure	9
	8.3	Trouble	shooting	9
9	Advan	ced instal	lation strategies	10
	9.1	Installin	g the CSD data and CSD-System software separately	10
	9.2	Running	g the installer at the command line	10
	9.3	Installin	g without GUI access	10
	9.4	Silent in	stall using the command line	11
	9.5	MSI-bas	ed installers	13
	9.6	Uninsta	llation using the command line	13
	9.7	Further	Help	13
10	CSD-C	rossMiner	·	14
11	WebC	SD Access		15
12	Startin	ig and Cor	nfiguring CSD System Software	16
	12.1	Window	/S	16
	12.2	Linux		16

	12.3	macOS				
	12.4	Using He	ermes to access CSD-Discovery functionality	16		
		12.4.1	Testing your Installation	17		
	12.5	Activatio	on of CSD System Components	17		
	12.6	Configu	ration of CSD System Components	17		
		12.6.1	ConQuest	17		
		12.6.2	Mogul	18		
		12.6.3	Mercury	18		
	12.7	Setting u	up the CSD System Environment on Linux and macOS	18		
	12.8	Unity de	esktop launchers for Ubuntu Linux	19		
13	CSD Python API			20		
	13.1	Use of t	he CSD Python API in Mercury	20		
	13.2	Use of t	he CSD Python API via the command line	20		
		13.2.1	Using the CSD Python API on Windows	20		
		13.2.2	Using the CSD Python API on Linux	20		
		13.2.3	Using the CSD Python API on macOS	21		
	13.3	Use of t	he CSD Python API with your own Python installation	21		
14	Licensi	Licensing Overview				
	14.1	Starting	the CCDC Software Activation tool graphical user interface	22		
		14.1.1	Windows	22		
		14.1.2	Linux	22		
		14.1.3	MacOS	23		
	14.2	Running	the command line CCDC Software Activation tool	23		
	14.3	Activatir	ng online with a CCDC licence activation key	23		
		14.3.1	Via the graphical user interface	24		
		14.3.2	Via the command line interface	24		
	14.4	Activatir	ng offline with a CCDC licence activation key	24		
		14.4.1	Via the graphical user interface	24		
		14.4.2	Via the command line interface	25		
	14.5	Setting u	up access to a local CCDC licence server	25		
		14.5.1	Obtaining the local CCDC licence server	26		
		14.5.2	Configuring access to the local CCDC licence server via the grund user interface version of the activation tool	raphical 26		
		14.5.3	Via the command line interface	26		
	14.6	Using th a system	e activation tool in administrative mode to allow access for al	l users on 27		
	14.7	Perform	ing licensing tasks with the CSD-System installer	27		
		14.7.1	Activate the CSD-System now	28		
		14.7.2	Use a CCDC local licence server	28		
	14.8	Commai	nd line use of the CSD-System installer	29		

15	Public IsoStar Server	30
16	CSD Software & Data Updates	30
17	Activating In-House Databases	31

1 CSD Release Package

The 2020.1 CSD Release installer is supplied via download, or via USB stick, for Windows, Linux and macOS. The installer contains:

- The Cambridge Structural Database, Version 5.41
- ConQuest 2020.1
- Mercury 2020.1
- enClFer 2020.1
- IsoStar 2020.1
- Mogul 2020.1
- CSD Conformer Generator 2020.1
- Hermes 2020.1
- GOLD 2020.1
- CSD Ligand Overlay 2020.1
- SuperStar 2020.1
- DASH 3.4.6 (Windows only)
- CSD Python API 3.0.2

Supported platforms are listed elsewhere (see Supported Platforms). Additionally, you may have access to other components that are supplied separately:

- CSD-CrossMiner 2020.1 (Windows only)
- WebCSD (accessed via https://webcsd.ccdc.cam.ac.uk)

Access to these will depend on what your licence gives you access to.

CSD-System

• ConQuest, Mercury, Mogul, IsoStar, WebCSD, enCIFer and the CSD Python API.

CSD-Materials

Everything in CSD-System as well as:

- Additional functionality within Mercury and the CSD Python API.
- Conformer Generator and DASH.

CSD-Discovery

Everything in CSD-System as well as:

- Additional functionality within Mercury and the CSD Python API.
- Hermes, GOLD, SuperStar, CSD Ligand Overlay, CSD-CrossMiner and Conformer Generator

CSD-Enterprise

All of the above

2 Database Content and Information

• The 2020.0 CSD Release contains 1,016,168 unique structures and 1,034,174 entries (CSD version 5.41). More structures will be made available in the CSD data updates throughout 2020.

3 What's New

See the following web page for an overview of what's new across the CSD Software Portfolio over the last 12 months: <u>https://www.ccdc.cam.ac.uk/solutions/whats-new/</u>

4 Known Problems

- Use of ConQuest's 3D Visualiser on Retina Displays: On macOS systems with retina displays only, there is a known issue with being unable to select atoms in ConQuest's 3D visualiser. We would recommend exporting your hits to Mercury for further analysis instead.
- Use of ConQuest, Mogul's sketcher and API scripts in Mercury/Hermes on Windows accounts where the username contains non-ascii characters: On some Windows systems where the user's username contains non-ascii characters or spaces this can cause problems with components of the CSD-System that use Python (specifically ConQuest, Mogul's sketcher and the API script interface in Mercury and Hermes). For ConQuest we would recommend adding the following line to the .csds_defaults3 file in your user home area to work around this issue:

csds_data_directory = 'C:\\conquest_workspace'

For API scripts, we would recommend use of a Python 3 install of the API if you encounter this issue, as Python 3 has better support for non-ascii characters.

 Use of the 'View diagrams' option in the 'Results and analysis' tab in Mogul results in a diagram that cannot be dismissed: The 'View diagrams' button in the 'Research and analysis' tab of Mogul can cause a Diagram to be displayed incorrectly on Windows & Linux systems, whereby the diagram cannot be closed and overlays the Mogul interface permanently. Currently the only solution is to close and restart Mogul.

5 Installation Overview

Sections 6 to 8 describe how to perform a typical installation, which is the recommended method of installing the CSD software and data. This will involve the following steps:

- Download the required CSD System installers from <u>http://www.ccdc.cam.ac.uk/csds_download</u>. This will require your Customer Number and Activation Key.
- 2. Install the CSD System Software and Database files for Windows (see Windows Installation), Linux (see Linux Installation), and/or for macOS (see macOS Installation) and registering the software.
- 3. Install the IsoStar 2020.1 server (Linux) (see IsoStar Server Installation).

More advanced methods of installation are also possible and are described in section 9.

5.2 System Requirements

5.2.1 Supported Platforms

Executables in this release are supported on the following platforms and operating systems, unless noted that some platforms are unavailable in section 1:

- Windows Intel compatible, 64-bit:
 - Windows 7 and 10
- Linux Intel compatible, 64-bit:
 - RedHat Enterprise 7 and 8
 - CentOS 7 and 8

Note: As we add support for newer versions of Linux, support for older versions may have to be withdrawn.

- macOS Intel compatible, 64-bit:
 - macOS 10.13, 10.14 and 10.15

If you choose to use a version other than those listed above we cannot guarantee that the 2020.1 CSD Release software will work correctly, although we will attempt to assist you with any problems you may encounter.

Linux platforms will require the Network Security Services (NSS) package to be installed (see Linux Installation below for more details)

5.2.2 Changes to Supported Platforms and Products

As detailed with the 2019 CSD Release, 32-bit Windows executables are no longer available. With this, and all future releases, executables will be supported on 64-bit only and will not be compatible with 32-bit operating systems. If you only have access to 32-bit Windows systems and need to continue accessing the older 2019 software which is 32-bit, please contact support@ccdc.cam.ac.uk.

The 2020 CSD Release no longer supports Python 2.7. The miniconda distribution we include with the CSD installation is now Python 3.7 and all standalone pip and conda packages are available for Python 3.7 only.

The 2020 CSD Release will be the last to support Windows 7, which is now no longer supported by Microsoft. It is intended that the 2021 CSD Release will drop Windows 7 support and thereafter we will support Windows 10 only for Microsoft Windows.

The cqbatch and mogulbatch command line utilities are now deprecated - while these still remain a part of the CSD System software during 2020, their use is no longer be recommended, and we would instead encourage switching to use of the CSD Python API. We anticipate that cqbatch will be removed entirely in the 2021 CSD Release.

If any of the above will cause insurmountable difficulties, please contact us at *support@ccdc.cam.ac.uk* to discuss possible solutions.

5.2.3 Graphics System Requirements

Products with 3D graphical display functionality are supported only on graphics cards and chipsets that have up to date installers and are still in support from the graphics system manufacturers. The graphics drivers in use should support OpenGL 2.1.

5.2.4 Access of CSD software by X-forwarding

Remote access of CSD software by X-forwarding, such as via ssh on Linux, or a mixed system such as use of an X-emulator on Windows to access a Linux installation, is not supported.

While such methods may work, success can depend on many variables, including both the remote and local system as well as any emulation software that may be used and we cannot fully test or provide support for all of these combinations. If you do encounter any difficulties, we would recommend using the native software for the platform you are accessing from, and if all possible do so locally rather than remotely. If disk space is a concern, a compromise can be installing the software locally and accessing a remote data install.

5.2.5 Stereoscopic Viewing Graphical System Requirements

Please check the following support solution on our website to see the most recent recommendations for 3D stereoscopic viewing in Mercury:

http://www.ccdc.cam.ac.uk/SupportandResources/Support/pages/ SupportSolution.aspx?supportsolutionid=284

We would appreciate receiving feedback to *support@ccdc.cam.ac.uk* on your experiences of using stereo display on different hardware configurations to those suggested in the support solution above, if successful, so that we may inform other users of valid hardware configurations. On machines without appropriate hardware, the **Stereo** checkbox will be disabled.

5.2.6 Disk Space Requirements

A complete installation of the 2020.1 CSD Release requires approximately 17 GB of disk space. This includes all software (3 GB) and all data files (14 GB).

6 Windows Installation

6.1 General Installation Options

On all platforms the installer will give you the option to install:

- CSD Software
- CSD Data

The default option is to install both the CSD Software and the CSD Data to the same location. However, it is possible to install the CSD Software and CSD Data separately. In this case we recommend installing the CSD Data to your desired location first, then re-run the installer and install only the CSD Software - you will be prompted to locate the CSD Data so that individual users will not need to do so themselves when first starting CSD software that requires it.

6.2 Installation Procedure

Administrator privileges are required for installation.

Do not install directly on top of a previous installation; use a new folder. We recommend that you uninstall previous versions of all CSD System software, any previous version of the CSD Python API, as well as Mogul and CSD database files, and remove all CSD update files, before you install the current version.

To install on Windows:

- 1. Download the csds-2020-windows.zip file and unpack its contents to a location on your computer. Note that the installer cannot be run from within the zip file and both the installer and dist file must be located in the same directory.
- 2. Double-click on the csds-windows.exe file. The installer menu will take you through the steps necessary to complete the installation.
- Installation will place ConQuest, Mercury, Mogul, Conformer Generator, IsoStar Client, enCIFer and DASH in a 'CSD_2020' sub-directory, and Hermes, GOLD and SuperStar in a 'Discovery_2020' sub-directory, and the CSD Python API in a 'Python_API_2020' sub-directory. Shortcuts to these programs will also be placed on your desktop and Start Menu (where available).

6.3 Uninstalling CSD System Software and Database files

The CSD System software can be removed from your computer by selecting:

Start Menu -> CCDC -> CSD System Software 2020 -> Uninstall CSD System 2020

7 Linux Installation

7.1 Package Requirements

The CSD system software requires the Network Security Services (NSS) libraries to be present on your system. These can be installed on CentOS/RedHat 7/8 with the command:

sudo yum install nss

7.2 Installation Procedure

Do not install directly on top of a previous installation. We recommend that you uninstall previous versions of the CSD system, database files including all CSD update files before you install the current version.

To install the CSD System, and/or data on Linux.

- 1. Download or csds-2020-linux-x64.tar and unpack its contents to a location on your computer. Note that both the installer and dist file must be located in the same directory.
- 2. Ensure that the installer executable has execute permissions via the command:

```
chmod a+x ./csds-linux-x64.run
```

3. In a terminal window as a **non-root** user on the machine you intend to run the CSD System, type:

./csds-linux-x64.run

4. Follow the on-screen instructions to install the software and databases.

7.3 IsoStar Server Installation

This step may be skipped entirely if you wish to use our publicly hosted IsoStar server at http://isostar.ccdc.cam.ac.uk.

The Linux IsoStar Server installer contains the IsoStar Software for all supported Linux platforms, as well as the IsoStar data files.

To install IsoStar on Linux:

- 1. Download the IsoStar-linux-x64-installer.run installer file.
- 2. Ensure that the installer executable has execute permissions via the command:

chmod a+x ./IsoStar-linux-x64-installer.run

3. In a terminal window as a **non-root** user on the machine you intend to run the CSD System, type:

```
./IsoStar-linux-x64-installer.run
```

4. Follow the on-screen instructions to install the software and databases.

8 macOS Installation

8.1 General Installation Process

Administrator privileges are recommended but not usually required for installation.

Do not install directly on top of a previous installation. We recommend that you uninstall previous versions of the CSD system, database files including all CSD update files before you install the current version.

We suggest that all software and database components are installed in the /Applications directory, which will usually require Administrator privileges. However, you are free to use any other location.

8.2 Installation Procedure

To install on macOS:

- 1. Download the csds-2020-osx.tar file and unpack its contents to a location on your computer.
- 2. Double click on csds-osx and follow the on-screen instructions to install the software and databases.

8.3 Troubleshooting

Operation of CSD Software on macOS requires an X server to be running in rootless mode such that X-Window applications can be successfully launched as separate windows on the console display. A suitable X11 server can be downloaded from *http://xquartz.macosforge.org*.

IsoStar is a client-server application and only the client software can be installed on Windows or macOS. A public IsoStar server is hosted at CCDC: *http://isostar.ccdc.cam.ac.uk*. Access to scatterplots from this public server requires a licensed copy of the IsoStar client package (see Public IsoStar Server). Alternatively, you can use an HTTP server to make the IsoStar data available. The HTTP server can be run on any of the supported IsoStar Linux platforms (see Supported Platforms). Please note that it is currently not possible to run the IsoStar server on Windows or macOS. Further information on setting up your HTTP server is provided (see IsoStar Server Installation).

On macOS, Safari does not employ Helper Applications so if this browser is being used to access IsoStar data you will need to download the scatterplot file then open the file within the IsoStar client manually. Alternatively, Firefox can be configured to launch an application associated with a particular file extension.

If you are experiencing any problems with installation or use of the CSD System, please review our support database at *http://www.ccdc.cam.ac.uk/support* where you should be able to find help with common issues.

9 Advanced installation strategies

There are several options to adjust the installation of the CSD-System to your needs.

9.1 Installing the CSD data and CSD-System software separately

It is possible to install the CSD data and the CSD-System software to different locations. This can be useful to, for example, have a single data installation on a network accessible location that multiple software-only installations can use. This will allow you to save space on the systems where the software is installed.

Using the standard graphical installation interface, you will have the option to install both data and software (the default), only the data, or only the software. To install the data to a different location, it is highly suggested to perform the data-only install first. If this is done, you can supply the path to the location of the data during installation of the software and have this location automatically used when running the software.

9.2 Running the installer at the command line

More advanced use of the CSD System installers usually involves running via the command line, which allows various arguments to be added that changes the installer's behaviour or provides information normally entered via installer dialogs.

Windows:

Ensure you are in the same directory as the .exe installer file and then just type its name, e.g.

csds-windows.exe

Linux:

You will normally need to specify the location of the installer executable to run it - this is most easily done by being in the same working directory as the .run installer executable and prepending ./ (which means "in this directory"), e.g.

./csds-linux-x64.run

macOS:

To run the installer application at the command line, ensure you are in the same working directory and use the open command, e.g.:

open csds-osx.app

9.3 Installing without GUI access

If you do not have graphical access to the machine where you are installing, the installation program can be run using a text-only interface. This can be useful for cases when running over slow connections or as a simplified interface. This interface should automatically be invoked if it senses there is not a graphical interface, but can also be manually specified if desired by adding the --mode text argument when running the CSDS installer at the command line, for example:

./csds-linux-x64.run --mode text

You will be walked through the same installation procedure as in the graphical interface and have the same options.

9.4 Silent install using the command line

The technology used by the CSD installers allows all data normally entered in the graphical installer interface to instead be specified directly via command line arguments when running the installer in a terminal window. This enables silent and unattended installation, which can be useful for mass deployments of the software in an automated fashion.

Running the installation program in a terminal/shell with the **--help** option will provide a complete list of the command-line options available. For example:

csds-windows.exe --help

Below are some of the more common options or scenarios.

- --mode unattended will force the installer to operate in batch/unattended mode. There are several associated options that are required for automated installations:
- --prefix give the root directory of the installation. On Linux, it will default to \$HOME/CCDC, on Windows to C:\Program Files\CCDC and /Applications/CCDC on macOS.
- --uattendedmodeui can take the values:
 - none for an unnattended silent install
 - **minimal** for limited feedback
 - minimalWithDialogs for dialog driven feedback if possible
- --Licensing can take the values of:
 - NotNow to skip registration. Activation will need to be completed manually later ActivateAfterInstall LocalLicenceServer NotNow
 - ActivateAfterInstall to attempt to activate the software automatically immediately after the installation process. Will additionally require the activation key. This mode requires the machine to have access to the internet as it will contact the CCDC licensing server.
 - LocalLicenceServer will use a specified existing local licence server. You will
 require the hostname or IP of the licence server, and the port it is using.
- --activation_key <activation_key> is used to in conjunction with --Licensing ActivateAfterInstall to activate the software during the installation process.
- --activate_admin true is used to in conjunction with --Licensing ActivateAfterInstall to activate the software during the installation process for all users of a system. This requires running as administrator or root user. This causes the software to auto-

activate online when each user first starts one of the components of the CSD-System.

- --server_host <server_host> and --server_port <server_port> are used in conjunction with –Licensing LocalLicenceServer to configure access to a local licence server.
- --server_admin true is used to in conjunction with --Licensing ActivateAfterInstall to setup access to a local licence server for all users of a system. This requires running as administrator or root user.
- --enable-components and --disable-components will enable and disable the installation of the data (datagroup) and the software (softwaregroup) components of the CSD-System. Allows the values:
 - datagroup installs the data component
 - vcredist (Windows only) installs the Microsoft Visual Studio runtime libraries required by the CSD software.
 - softwaregroup installs the software component. This option additionally allows the specification of the location of your data install:
- --csdsoftwareonly
 - true enables definition of the data directory via --csdsoftwareonlydatadir
 - false no link to a data directory will be carried out (default)
- --csdsoftwareonlydatadir <data directory> should be set to the location of the main CSD database files, for example on Windows: "C:\Program Files\CCDC\CSD_2020\CSD_541"

Note that if an argument contains a space you will need to enclose it in double quotes. This is most common with Windows paths that contain elements like "Program Files".

The two most common scenarios are for batch mode installations with activation during installation:

Windows

- o csds-windows.exe --prefix "C:\Program Files\CCDC" --mode unattended --unattendedmodeui none --Licensing ActivateAfterInstall --activation_key 123456-123456-123456-123456-123456
- Linux
 - o ./csds-linux-x64.run --prefix /soft/ccdc --mode unattended --unattendedmodeui none --Licensing ActivateAfterInstall --activation_key 123456-123456-123456-123456-123456
- macOS
 - o open csds-osx.app --prefix /Applications/CCDC --mode unattended --unattendedmodeui none --Licensing ActivateAfterInstall --activation_key 123456-123456-123456-123456-123456

or with a local licence server for all users (must be run as administrator or root user):

- Windows
 - o csds-windows.exe --prefix "C:\Program Files\CCDC" --mode
 unattended --unattendedmodeui none --Licensing
 LocalLicenceServer --server_host myserver --server_port 1234 server admin true
- Linux

- o ./csds-linux-x64.run --prefix /soft/ccdc --mode unattended -unattendedmodeui none --Licensing LocalLicenceServer -server host myserver --server port 1234 --server admin true
- macOS
 - o open csds-osx.app --prefix /Applications/CCDC --mode unattended --unattendedmodeui none --Licensing LocalLicenceServer -server_host myserver --server_port 1234 --server_admin true

9.5 MSI-based installers

MSI (MicroSoft Installer) based installers are available as an alternative to the Bitrock installers we provide by default. MSI-based installers are mainly of use for those organisations that have mechanisms in place to deploy using Microsoft technologies that require MSI-based installers. If this would be of use to your organisation please contact support@ccdc.cam.ac.uk.

The MSI installers are provided as separate software and data installers. During install time, if the data is not being installed on the same computer then the software installer allows the user to select where the data is installed. If installing silently, the following msi parameters will achieve the same result:

USE NETWORK CSD DATA=1 DATABASE PATH="C:\path\to\CSD 541"

9.6 Uninstallation using the command line

In much the same way as the installer executable, the uninstaller that is created in the CSD_2020 installation folder can also be run either interactively via a GUI, or at the command line. Like the installer executable, you can view the options available with the uninstaller by using the **--help** argument, e.g.

uninstall.exe --help

To perform a silent uninstall with no further user prompts, use:

csds-windows.exe --mode unattended

Note that it can take some time for the uninstall to complete.

9.7 Further Help

Visit our installation support page at <u>https://www.ccdc.cam.ac.uk/csds_install_help</u>. This page contains all of the above details and will also be updated with further assistance as we determine other use cases that would be useful to highlight.

10 CSD-CrossMiner

CSD-CrossMiner is available as a separate download to the main CSD System installer and is available for 64-bit Windows, Linux and macOS systems only. Use of CSD-CrossMiner will require a CSD-Discovery or CSD-Enterprise level licence.

To install CSD-CrossMiner, download and follow the installation instructions provided with the download links from the CSDS download page on the CCDC website (https://www.ccdc.cam.ac.uk/csds_download).

11 WebCSD Access

The CCDC hosts a WebCSD server which can be accessed at:

http://webcsd.ccdc.cam.ac.uk

Access to this server can be set up by IP address if you send us your IP ranges or you can register a username and password in order to obtain access. If your institution has purchased a campus licence you will receive unlimited, site-wide access to WebCSD.

Those with unlimited site licenses can contact admin@ccdc.cam.ac.uk with details of their institution's IP address range(s) in order to arrange access.

12 Starting and Configuring CSD System Software

12.1 Windows

To start any CSD system software component on Windows select the appropriate link from the Windows Start menu:

Programs -> CCDC -> CSD System Software 2020

Or use one of the desktop shortcuts created for ConQuest, Mogul, Mercury, IsoStar, enCIFer, DASH, Hermes and GOLD by the installation process.

12.2 Linux

Using a command line console, change directory to <INSTALLDIR>/CSD_2020/bin (where <INSTALLDIR> is the path to your CSD_2020 installation directory), or ensure that this is in your system PATH.

Then for ConQuest, type:

сq

For Mogul, type:

mogul

For Mercury, type:

mercury

For IsoStar client, type:

run_isostar

For Discovery software, change directory to <INSTALLDIR>/Discovery_2020/bin (where <INSTALLDIR> is the path to your Discovery_2020 installation directory), or ensure that this is in your system PATH.

Then for Hermes, type:

hermes

For the GOLD interface in Hermes, type:

gold

12.3 macOS

To start any CSD system software component on macOS click on the appropriate icon in the Dock, or in the installation folder for ConQuest, Mercury, Mogul, IsoStar, enCIFer, Hermes and GOLD.

12.4 Using Hermes to access CSD-Discovery functionality

Hermes acts as both a visualiser and as an interface and client for GOLD, SuperStar and the CSD Ligand Overlay. Access to these requires a CSD-Discovery enabled licence.

SuperStar and the CSD Ligand Overlay can be accessed via the Calculate menu and GOLD can be accessed via the GOLD menu.

To start Hermes or GOLD, please refer to the instructions given in earlier in this section.

12.4.1 Testing your Installation

A number of tutorials are available to complement the software. To test your installation and to learn something about the features of the software, it may be useful to try one or more of these tutorials which are located in the examples sub-directories of each GOLD Suite product.

Tutorial 1 involves PDB entry 1ACM. This is aspartate carbamoyl transferase complexed with a phosphonated, polar peptide ligand.

To use GOLD to dock the peptide ligand into aspartate carbamoyl transferase perform the steps outlined in the GOLD documentation for Tutorial 1.

The top level of the HTML version of the documentation can be found in the docs subdirectories of each GOLD Suite product.

12.5 Activation of CSD System Components

The CSD System Installer will offer you the opportunity to activate the CSD System as part of the installation process, either by accessing our online activation servers, or by entering details of a local licence server. Activation online will require your activation key.

If a valid licence is not present, then when using any component of the CSD System software (i.e. ConQuest, Mogul or IsoStar client) for the first time you will be prompted to activate.

For more information about activation and licensing (see CSD System Software Licensing).

Mercury and enCIFer may be installed and used with a free CSD-Community licence. Activating with a CSD-System or greater licence will, however, allow access to additional features that are only available to CSD system users.

12.6 Configuration of CSD System Components

12.6.1 ConQuest

Search Data Directory

Before using ConQuest you may be required to identify a Search Data directory. This will be used to store temporary files for running searches. It will also be the default directory for saving some ConQuest files.

Database Location

Before using ConQuest you may be required to locate the main database files. The location of these files is identified by selecting a CSD database information file. For ConQuest this file will be called as541be.inf and will be found in the csd subdirectory in the location where you installed the database files.

Viewing PDF files Produced by ConQuest

ConQuest is able to generate PDF files for viewing or printing entries from the CSD (including 2D diagrams).

In order to view or print these files you will need to use a PDF reader, such as Adobe Acrobat Reader. Adobe Acrobat Reader is available from the Adobe web-site: http://www.adobe.com. Other free PDF readers are available, see https://pdfreaders.org

12.6.2 Mogul

Database Location

Before using Mogul, you may be required to locate the main database files (as detailed for ConQuest above) as well as the mogul database files. The location of these files is identified by selecting a mogul path information file. For Mogul this file will be called mogul541.path and will be found in the data subdirectory in the location where you installed the database files.

12.6.3 Mercury

When Mercury is launched, it tries to detect whether or not the CSD is installed. If the CSD can be found, it is opened, and the structure navigator on the right-hand side of the main Mercury window will then contain the refcodes of all the entries in the database.

If you have a CSD-format database that is not detected automatically by Mercury, you can open it by clicking Databases, followed by Database Location... Once opened, the database will be added to the Databases menu.

You can use Mercury to view either your own crystal structures, or those retrieved from a ConQuest search. To view the hits from a ConQuest search in Mercury select Analyse Hitlist, from within ConQuest, and then View in Mercury from the pull-down menu. Alternatively, within ConQuest, select File from the top-level menu and View in Mercury from the resulting pull-down menu.

Different Mercury features are unlocked depending on your licence.

12.7 Setting up the CSD System Environment on Linux and macOS

Setting the CSDHOME environment variable on Linux and macOS can aid in the location of the CSD software and data installation if you have a non-standard setup. Additionally, adding <INSTALLDIR>/CSD_2020/bin and <INSTALLDIR>/Discovery_2020/bin to your PATH on linux can allow you to start the CSD software without use of the full path to its location.

For example:

 To set CSDHOME for Bourne shell (sh) or Korn shell (ksh), type: CSDHOME=<INSTALLDIR>/CSD_2020; export CSDHOME where <INSTALLDIR> is the top level CCDC directory of your CSD System installation.

For example:

CSDHOME=/usr/local/CCDC/CSD_2020; export CSDHOME Or CSDHOME=/Applications/CCDC/CSD 2020

2. Similarly, to set CSDHOME for C-shell (csh), type:

setenv CSDHOME <INSTALLDIR>/CSD_2020

For example:

setenv CSDHOME /usr/local/CCDC/CSD 2020

```
PATH=<INSTALLDIR>/CSD_2020/bin:<INSTALLDIR>/Discovery_2020/bin: $PATH; export PATH
```

4. Or for C-shell (csh) type:

```
setenv PATH
<INSTALLDIR>/CSD_2020/bin:<INSTALLDIR>/Discovery_2020/bin:$PATH;
rehash
```

To make these changes permanent, add the commands executed in steps 1 and 2 to all your CSD System users' .login (csh) or .profile (sh, ksh) files. Alternatively, place the commands in a system-wide login or profile script such as /etc/profile.

12.8 Unity desktop launchers for Ubuntu Linux

The CSD software now installs .desktop files suitable for use with the Unity desktop's launcher mechanism.

The files are installed into the CSD_2020/desktop and Discovery_2020/desktop directories of your linux installation for the respective programs that can be launched from the CSD software in those locations.

To associate a CCDC application with the Unity Launcher, use the command 'sudo desktop-file-install application.desktop', which will require your account to be able to run commands as root via sudo. For example, to add IsoStar use:

```
sudo desktop-file-install isostar.desktop
```

Once done, you should find that application now appears as a searchable application to launch in the Unity interface.

In order to allow the 'Open With' dialog in browsers on Ubuntu 16 to offer IsoStar or Hermes as options when viewing IsoStar scatterplots or mol2 files, this step will be required with the isostar.desktop and hermes.desktop files respectively.

See <u>https://help.ubuntu.com/community/UnityLaunchersAndDesktopFiles</u> for more details.

13 CSD Python API

The 2020.1 CSD Release includes a version of the CSD Python API and a distribution of miniconda Python in order to allow for easy use. This will be automatically installed together with the CSD software.

13.1 Use of the CSD Python API in Mercury

The CSD Python API menu in Mercury allows the running of Python scripts in an interactive manner, typically acting on the currently viewed structure. This menu should default to using the included miniconda python installed in the Python_API_2020 directory alongside the CSD software. The **Options...** menu may be used to specify a different Python installation or clicking the **Default** button will return to using the bundled version of the API.

For more details on the use of the API in Mercury, please refer to the Mercury User Guide.

13.2 Use of the CSD Python API via the command line

The CSD Python API can also be used via the command line. The CSD System installer will setup some convenient shortcuts and/or scripts to allow you to start the API with the correct environment already set. More details on using the Python API can be found in the CSD Python API documentation.

13.2.1 Using the CSD Python API on Windows

A Python command prompt may be started via the 'CSD Python API' shortcut that will have been created on your desktop, or in the Windows Start Menu.

To run in an existing command prompt window, navigate to the Python API 2020\miniconda directory and type 'python'.

13.2.2 Using the CSD Python API on Linux

Start a terminal and navigate to the Python_API_2020 directory. To get a Python prompt where the API can be used, run the 'run_csd_python_api' script. A Python terminal should start, reporting Python version 3.7.1.

To set up the environment correctly in the terminal without starting Python, navigate to the miniconda/bin directory and type:

source activate

A (root) prompt should appear at the start of the command line prompt, indicating that the correct environment should have been created. The miniconda Python is now the default to be started by just typing 'python'.

To go back to a normal terminal, type the following in the miniconda/bin directory:

source deactivate

13.2.3 Using the CSD Python API on macOS

Open Finder and navigate to the Python_API_2020 folder. To get a Python prompt where the API can be used, double-click on the 'run_csd_python_api' script. A Python terminal should start, reporting Python version 3.7.1.

The run_csd_python_api script can also be run from a terminal.

To set up the environment correctly in the terminal without starting Python, navigate to the miniconda/bin directory and type:

source activate

A (root) prompt should be created, and the correct environment for macOS will now be set to allow use of Python scripts that utilise the API. To deactivate, type:

source deactivate

13.3 Use of the CSD Python API with your own Python installation

The CSD Python API may be installed into your own Python installation via use of pip or conda package managers. This method of use is recommended only for expert Python users who are experienced with installing Python packages.

14 Licensing Overview

CSD System software is licensed on a node-locked basis. Your site has a Licence of Access Agreement that entitles you to install the CSD System on a specified number of machines.

The first time you attempt to run any of the CSD System components (e.g. ConQuest, Mercury, Mogul) on a particular machine that has not been activated you will be prompted to activate the installation using the process described below.

Note: For those institutions with a site licence local licence server alternative is available. This mechanism provides site-wide access to the CSD without the need to activate individual machines, by accessing your local licence server instead of activating online.

CCDC licensing is primarily *node-locked* which means that each licence is tied to a specific computer system. In order to use CCDC software there are primarily three methods to access the software:

- 1. Activate access to free CSD-Community features (e.g. Mercury, enCIFer)
- 2. Activate additional features with a CCDC licence activation key
- 3. Access a local licence server that has been set up and started on your network

To facilitate this process, your CCDC software installation will contain the CCDC Software Activation tool. This may be accessed in an interactive way by a graphical user interface, or at the command line by passing appropriate arguments. Additionally, you may select the option to perform activation or setting up access to a local licence server when performing an installation of the CSD System.

14.1 Starting the CCDC Software Activation tool graphical user interface

14.1.1 Windows

The CCDC Software Activation tools will be located in the

<INSTALLDIR>\CSD_2020\Software Activation

folder of a CSD System installation, or

<INSTALLDIR>\Software Activation

in other CCDC product installers. To start the graphical user interface, double-click on *ccdc_activator_gui.exe*

14.1.2 Linux

The CCDC Software Activation tools will be located in the <*INSTALLDIR*>/*CSD_2020/bin*

folder of a CSD System installation, or

<INSTALLDIR>\software_activation

in other CCDC product installers. To start the graphical user interface, run ccdc_activator_gui

14.1.3 MacOS

The CCDC Software Activation tools will be located in the

<INSTALLDIR>/CSD_2020

folder of a CSD System installation, or

<INSTALLDIR>\Software_Activation

in other CCDC product installers. To start the graphical user interface, double-click the CCDC-Software-Activation application.

14.2 Running the command line CCDC Software Activation tool

The command line variant of the CCDC Software Activation tool may be found in the same location as the graphical user interface version detailed above. You will need to start a command line prompt/terminal and then:

On Windows run: ccdc_activator.exe

On Linux run:

./ccdc_activator

On MacOS run:

./CCDC-Software-Activation.app/Contents/MacOS/ccdc_activator.x

This should display the available command line arguments that may be passed to the activation tool. To perform activation or setup of a local licence server, the correct arguments will need to be provided. These are detailed in each licence activation/setup type below.

14.3 Activating online with a CCDC licence activation key

If you have purchased a CCDC product such as the CSD-System, then you will have been provided with an activation key. This key can be used to perform an activation on the computer system you are using the CCDC software, and the easiest method to do so is by directly communicating with our licence server. This will require internet access on the computer you wish to activate. If you have previously activated with another licence key, you can enter a new one to change to use that licence.

This will utilize one of your available licenses and allow use on that computer for any user. Note that each user will need to activate the CCDC software individually, although this will use the same single licence seat if performed on the same computer system. It is also possible to configure your system to auto-activate for all users.

14.3.1 Via the graphical user interface

- 1. Start the CCDC Activation Tool as described above.
- 2. Click on the Activate online tab if it is not already selected.



3. Copy and paste the activation licence key into the box and then click on the *Activate* button. You should be informed that activation was successful. Access to the CCDC products and features your licence allows should now be possible.

14.3.2 Via the command line interface

Run the *ccdc_activator* command line tool with the *-a* and *-k* arguments, followed by your activation key. For example, on Windows:

ccdc_activator.exe -a -k 123456-123456-123456-123456-123456-123456

14.4 Activating offline with a CCDC licence activation key

If you have an activation key but the system you are installing on has no direct internet access, then you can instead utilize the *Activate offline* option. This will save licensing information from the target computer and allow you to use another internet enabled computer elsewhere to complete activation. If you have previously activated with another licence key, you can enter a new one to change to use that licence.

14.4.1 Via the graphical user interface

- 1. Start the CCDC Activation Tool as described above.
- 2. Click on the Activate offline tab if it is not already selected.



- 3. Copy and paste the activation licence key into the box and then click on the *Generate Offline Request* button. You will be prompted to save a LicenceRequest.licreq file to your computer.
- 4. Transfer this file to an internet enabled computer and email it to <u>admin@ccdc.cam.ac.uk</u> together with your customer/site identifier. The request will be processed by CCDC and a response file will be sent back to you. Transfer this file back to the target system.
- 5. Repeat steps 1-3 but this time use the *Apply Offline Response* button to select the response file sent to you by CCDC.
- 6. You should be informed that activation was successful. Access to the CCDC products and features your licence allows should now be possible.

14.4.2 Via the command line interface

Run the *ccdc_activator* command line tool first with the *-k* argument, followed by your activation key, then the *-g* and *-f* arguments followed by a file location to save the request file. For example, on Windows:

ccdc_activator.exe -k 123456-123456-123456-123456-123456-123456-g -f C:\Users\myusername\LicenceRequest.licreq

Send the request file to <u>admin@ccdc.cam.ac.uk</u>. A response file should be returned to you – complete activation with the -o argument instead of -g:

ccdc_activator.exe -k 123456-123456-123456-123456-123456-123456-0 -f C:\Users\myusername\LicenceResponse.licreq

14.5 Setting up access to a local CCDC licence server

If you have an unlimited site-wide licence for CCDC products, then it is possible to request access to a local licence server that can be installed within your network. You can then allow individual installations to access that local licence server to get permission to run, instead of performing node-locked activations. If you have previously activated with another licence key, or set up use of a different local licence server, you can enter new details to change to use that licence instead.

14.5.1 Obtaining the local CCDC licence server

To obtain the local CCDC licence server, please send a request to <u>admin@ccdc.cam.ac.uk</u>, quoting your customer details and existing node-locked activation key.

The local licence server is provided as an installer for MacOS, Linux or Windows and should be installed on a physical machine (it is NOT possible to use the local licence server on a virtual machine). More detailed instruction for installation and configuration of the local CCDC licence server are provided with the installers.

Once installed, you will need to know the hostname (or IP address) of the system it is installed on, as well as the port number it has been configured to use. This information is used by each client that connects to the licence server.

14.5.2 Configuring access to the local CCDC licence server via the graphical user interface version of the activation tool

- 1. Start the CCDC Activation Tool as described above.
- 2. Click on the Configure Local Server tab if it is not already selected.



- 3. Copy and paste the server hostname or IP address into *Server host* and select the port number the local licence server is using in *Port*.
- 4. You should be informed that activation was successful. Access to the CCDC products and features your licence allows should now be possible.

14.5.3 Via the command line interface

Run the *ccdc_activator* command line tool with the *-s* argument, followed by the URL and port that the server is running on in the format http://myserver:port. For example, on Windows:

ccdc_activator.exe -s http://myserver:1234

14.6 Using the activation tool in administrative mode to allow access for all users on a system

It is possible to use the activation tool to configure the licensing system to either autoactivate for all users of a system, or else configure all users to connect to a local licence server. To do so, the command line *ccdc_activator* tool must be used as Administrator or root (depending on the system in use). This is primarily intended as a means for system administrators to deploy the CSD Software and not require any licensing action by individual users.

To use the *ccdc_activator* tool in administrative mode, use the *-A* argument as an addition to one of the commands detailed above. For example, to set up a CSD installation to attempt to auto-activate with a particular key for users of that system use:

ccdc_activator.exe -A -a -k 123456-123456-123456-123456-123456-123456

To set up all users to connect to a local licence server at http://myserver:1234 use

ccdc_activator.exe -A -s http://myserver:1234

14.7 Performing licensing tasks with the CSD-System installer

It is possible to both activate the CSD-System and setup access to a local licence server when using the CSD-System installer. If installing as an administrator or root user, then this allows you to both install to a system and set up licensing so that the end user can immediately start using the software.

When installing the CSD-System, you will be presented with the following dialog:

you tiva	have an activation key, or details of a local licence server, then you may enter these details now in order to te the CSD System for the user running this installer. You can also elect to activate the software later by the
DC	Activation tool that this installer will install. Activate the CSD System now
C	Use a CCDC local licence server I have previously set up
С	Activate later via the CCDC Activation tool

You may select to either activate the CSD-System now, Use a CCDC local licence server, or you can choose to perform activation later with the CCDC activation tool as described in the earlier sections.

14.7.1 Activate the CSD-System now

You will be presented with the following dialog which allows you to enter your activation key.

Setup	-		×
Registration Details			C
Please enter your activation key below. This will be used to activate the CSD software a running this installer.	fter installatio	n for the	user
Activation Key			
Activate for all users of this system?			
○ Yes			
No			
Use of this software is governed by an agreement between CCDC and your organisation	n.		
Click here to view a copy of the standard Licence Agreement			

If you have administrator or root user access, then you will also be able to select whether to perform this activation for all users. Selecting 'no' (which is also the default option) will activate only for the user that is carrying out the installation, selecting 'yes' will set up the install to perform an auto-activation with the entered activation key when a user first starts a CSD-System software application.

14.7.2 Use a CCDC local licence server

You will need to have first set up a local licence server on your network and know the hostname (or IP address) and port number that it uses. You will then see this dialog:

🕒 Setup				\times
Setup local licence server				C
Please enter the hostname (or IP address) and port number that you Hostname or IP Port	r local CCDC licence :	server is runni	ng on.	
Setup licence server for all users of this system? O Yes (No				
InstallBuilder	< Back	Next >	Ca	incel

You will need to enter the hostname or IP address of your local licence server, as well as the port that it has been configured to use. If installing as an administrator or root user, you can also select to install for all users of the system, or just for the user performing the installation (the default).

14.8 Command line use of the CSD-System installer

The CSD-System installer can also be used at the command line by providing suitable arguments. Please see the following support FAQ that details the current command line options available in the installer: <u>https://www.ccdc.cam.ac.uk/csds_install_help</u>

15 Public IsoStar Server

A public IsoStar server is hosted at CCDC: *http://isostar.ccdc.cam.ac.uk*. Access to scatterplots from this public server requires a licensed copy of the IsoStar client package.

16 CSD Software & Data Updates

It is possible to check for the existence of software and data updates which are made available at regular intervals (approximately every 3 months). This will keep your software and copy of the CSD database more current between each major release of the CSD System.

Updates can be obtained automatically via the **Help... Check For Updates** option in either Mercury or Hermes. Specific updates for the CSD-CrossMiner installation, if you have one installed, can be obtained automatically via the equivalent option within CSD-CrossMiner.

Alternatively, the following URL will take you to the CCDC download page where the updates can be obtained manually as they become available:

https://www.ccdc.cam.ac.uk/support-and-resources/downloads/

You will be required to enter your Customer Number and Activation Key in order to download an update. For data updates only:

- Updates will need to be downloaded in numeric order and added to the same directory as your CSD database files.
- Follow the instructions for installation and the update(s) will be visible when restarting ConQuest.

Note: You will need write permission to the main CSD folder to install each update.

- Each update will be shown separately in the View Databases menu.
- The update packages can be searched either with the main database or separately as desired; this is controlled via options in the *Search Setup* dialogue box:

🕌 Search Setup	
Search Name: search1	Filters Advanced Options
Available Databases: 🔽 Show Updates separately	☐ 3D coordinates determined
CSD version 5.34 (November 2012)	□ R factor ⓒ <= 0.05 ○ <= 0.075 ○ <= 0.1
	Not disordered No errors
You can search complete database(s) or a subset (e.g., hits found in a previous search) Select Subset	Not polymeric No ions No cons
Single query being used. Search will find structures: where this query is true: Query 1	Only Organics Organometallic
Start Search	Cancel Reset

17 Activating In-House Databases

Since the 2019 CSD Release, ConQuest and the other CSD-System programs no longer recognize our old ASER format database (*.ind*, *.msk* and *.tcd*). In order to use an existing ASER database you will first need to convert it to our new database format. Details on how to do so can be found in this support FAQ: <u>https://www.ccdc.cam.ac.uk/support-and-resources/support/case/?caseid=d5e44a8b-41ee-e811-9044-005056975d8a</u>

ConQuest can search in-house databases in addition to the main CSD. These databases are created using the PreQuest or similar utilities. If you have created an in-house database that you wish to search using ConQuest you must first activate it using the procedure described below.

In order to activate your in-house database, you must copy (or soft-link: Linux only) the inhouse database file (*.sqlite*) to the same directory as the CSD V5.41 database files. On Linux this is typically:

```
<INSTALLDIR>/CSD 2020/csd
```

While on Windows, this is normally:

```
C:\Program Files\CCDC\CSD 2020\CSD 541
```

And on macOS:

```
/Applications/CCDC/CSD 2020/DATA/CSD 541
```

You must then run the Activate program.

1. For Linux, ensure that <INSTALLDIR>/CSD_2020/bin is in your PATH and type:

activate

To run the activate database program on Windows select:

```
Programs -> CCDC -> CSD System Software 2020-> Activate in-house database
```

from the Windows Start menu.

On macOS, start a terminal window and run the command:

```
/Applications/CCDC/CSD_2020/conquest.app/Contents/Resources/bin /activate
```

Note: Windows 7 and 10 users will require escalated administrator privileges to activate databases. To do so, right-click on the **Activate Inhouse Databases** menu item and select **Run as Administrator**.

In all cases a pop-up window like the one shown below will be displayed:

🕌 Prepare Inhouse Database(s) for use in ConQuest				
Activating an Inhouse Database for use with ConQuest				
Directory containing databases	C:\Program Files (x86)\CCDC\CSD V5.34	Change		
Database to activate	inhouse_db	_		
Database Name (e.g. 'Inhouse1')	mydatabase1			
Database Version (e.g. '1.1')	1.5			
Database Date (e.g. 'April 2001')	Jan 2013			
Search/Display Order	Before CSD v 5.34			
-	Activate	Exit		

The activation program attempts to find the directory where the database is located by examining your ConQuest defaults file. However, if the correct directory cannot be found then use the **Change** button to locate the required directory.

All databases in the selected directory which have *not* been activated will be displayed in the **Database to activate** pull-down menu. Simply select the databases you wish to activate.

The contents of the **Database Name** dialogue box will be used by ConQuest to identify which database you wish to search or view. Choose a name relevant to the database contents.

Enter a version number for the database in the **Database Version** dialogue box. If you have an earlier version of a database, with the same Database Name in the same directory, it is important to make sure that the most recent version has the largest version number so that it is used in preference to the others.

Enter the date for the database in the Database Date dialogue box.

Use **Search/Display Order** pull-down menu to select the order in which activated databases will be displayed and searched by ConQuest. Taking the above example, if you select **After CSD v5.41**, when both databases are selected for searching in ConQuest the main CSD database will be searched before the in-house database.

When you are happy with your selections, press the **Activate** button. This will create a .inf file for the database, which will then be viewable and searchable the next time you start ConQuest. You can activate additional databases by repeating the procedure described above.

To close the *activate database* program press the **Exit** button.

🕌 Search Setup	
Search Name: search1	Filters Advanced Options
Available Databases:	3D coordinates determined
CSD version 5.31 (November 2009)	□ R factor ⓒ <= 0.05 ○ <= 0.075 ○ <= 0.1
You can search complete database(s) or a subset (e.g., hits found in a previous search)	 Not disordered No errors Not polymeric No ions
Single query being used. Search will find structures: where this query is true:	No powder structures Only Organics Organometallic
Start Search Cano	cel Reset